



TECKNET

GM269 Wired Gaming Mouse



Welcome Guide

Product Layout



Technical Specifications

Button Count: 6 buttons
Resolution: 1000/1500/2500/4000/7200DPI
Interface: USB version 2.0
Operating Voltage: 5V
Operating Current: ≤200mA
Sleep Current: ≤19mA
Cable Length: 1.8m
LED Colour: Red (DPI 1000), Blue (DPI 1500), Green (DPI 2500), Purple (DPI 4000), Yellow (DPI 7200)
Macro Settings: 7
Profile Settings: 6
Dimensions: 125.3 x 68.5 x 39.5mm
Weight: 136.5g

Package Contents

1 x Gaming Mouse
1 x User Manual
1 x Warranty Card

System Requirements

To use this mouse, your computer must meet the following hardware requirements and run one of the operating systems listed below.

- PC with a Pentium processor or equivalent AMD processors
- USB 2.0
- WIN XP/WIN Vista/WIN 7/WIN 8/WIN10/Linux

Note: The scroll wheel only works under the operating systems listed above. If you use the mouse under a different operating system, the mouse may either not work or lose its enhanced features.

DPI Switch

The mouse supports 1000/1500/2500/4000/7200DPI. To change the DPI setting, press the DPI button. The default setting is 1000 DPI and LED indicator shows red colour. Click the "DPI" button on the top of the mouse once to change the DPI. The LED will change from Red (DPI 1000), Blue (DPI 1500), Green (DPI 2500), Purple (DPI 4000), Yellow (DPI 7200) one by one.

GM269-V2 Software Instructions Installation:







1. Scan the QR code below to enter the website to download and install the GM269-V2-Driver or manually enter the URL below to download and install <http://www.tecknetonline.com/download/MouseKeyboard/GM269-BLACK-V2.exe>



2. Click "Install" to start installation.









3. Click "Next Step"



2. Click "Install" to start installation.









3. Click "Next Step"



2. Click "Install" to start installation.









3. Click "Next Step"



2. Click "Install" to start installation.









3. Click "Next Step"



2. Click "Install" to start installation.









3. Click "Next Step"



2. Click "Install" to start installation.









3. Click "Next Step"



2. Click "Install" to start installation.









3. Click "Next Step"



2. Click "Install" to start installation.









3. Click "Next Step"



2. Click "Install" to start installation.









3. Click "Next Step"



2. Click "Install" to start installation.









3. Click "Next Step"



2. Click "Install" to start installation.









3. Click "Next Step"



2. Click "Install" to start installation.









3. Click "Next Step"



2. Click "Install" to start installation.









3. Click "Next Step"



2. Click "Install" to start installation.









3. Click "Next Step"



2. Click "Install" to start installation.









3. Click "Next Step"



2. Click "Install" to start installation.









3. Click "Next Step"



2. Click "Install" to start installation.









3. Click "Next Step"



2. Click "Install" to start installation.









3. Click "Next Step"



2. Click "Install" to start installation.









3. Click "Next Step"



2. Click "Install" to start installation.









3. Click "Next Step"



2. Click "Install" to start installation.








3. Click "Next Step"




2. Click "Install" to start installation.




3. Click "Next Step"



Macro Setting
GM269-V2 software supports 7 macro settings.
New Macro setting: Click "Macro manager"




2) Click "Start Recording" to set up the macro. Input the keys needed and click "Stop Recording" to save. Then click "OK" to save the setting. Click "Apply" to save the settings before exiting the software.




4) You can choose additional functions "Number of Loops", "Record delay between keystrokes" before or after macro recording. Then click "OK" to save the setting. Click "Apply" to save the settings before exiting the software.




6) After finish macro recording, go to main interface, choose the button you need, select "Macro" when the pop-up window appears, Click [X] and the saved macro will appear on the drop-down menu. Select the macro you need, then click "Apply" to save the settings, the macro for captioned key is ready for use.




Reset Factory Default
Select the profile you need, click "Reset" and "OK".



1) Click "New" to create a macro, when the pop-up window appears, input the keys needed. Take "a" for example, input "a" then press "Click" to save the macro.





3) You can modify the macro by click "Right Button" to modify the key action. Once finish modification then click "OK" to save the setting. Click "Apply", "OK" to save the settings before exiting the software.





5) You can delete the macro from the list. Simply select the captioned macro and click "Delete". Then click "OK" to save the setting. Click "APPLY" to save the settings before exiting the software.



Parameter Setting
You can adjust the speed of "DPI Setting", "Lighting", "Polling Rate", "Mouse Speed", "Double-Click Speed", "Scroll Speed" in this section, click "Apply" to save the setting.



Profile Setting
GM269-V2 supports 6 profiles setting.



Export Profile
1. You can export the profile after saving a profile, click "Save".

